



Xton Access Manager

INSTALLATION GUIDE (WINDOWS)

UPDATED AUGUST 2017

Contents

Introduction	2
Technical Support	2
Xton Access Manager	3
Privileged Account Management	3
Privileged Session Management	3
Privileged Job Management	3
Software Components	3
Architectural Diagram	3
Services	5
Active Directory or LDAP Integration	5
Planning your Installation and Deployment	5
Installing Xton Access Manager	5
System Requirements	6
Software Requirements	6
External Database	6
Installation	6
License Agreement	7
Components	8
Installation Location	11
System Administrator	12
SSO Connect	13
Load Balancer	14
External Database	15
Active Directory Integration	16
Summary	17
Completing the Installation	19
Logging into Xton Access Manager	20
Initialize	20
License Registration	21
Manual Registration	22
Uninstalling Xton Access Manager	22
Uninstaller	22



Database Cleanup 22

Appendix..... 23

Remote Session Manager Configuration..... 23



Introduction

This guide is designed to show system administrators how to install, initialize and run Xton Access Manager on a Windows host. For administration and user guide documentation, please visit our support section. <https://www.xtontech.com/resources>

Technical Support

If at any time you encounter an issue, have questions or need guidance, please contact us using the information provided in our Help section. <https://www.xtontech.com/company/contact-us/>



Xton Access Manager

Xton Access Manager (XTAM) is an agentless solution that provides a secured database to manage privileged accounts and secrets, establishes secure sessions for users through a standard web browser and automates the execution of jobs or tasks without disclosing or sharing access.

The purpose of this guide is to perform a new installation and first time system initialization. At the conclusion of this guide, XTAM will be ready for system configuration and use.

The target audience is system administrators with knowledge of computer administration, Active Directory and (optionally) database connectivity.

XTAM is installed to a Windows or Unix computer (physical or virtual), with optional connection to Active Directory or LDAP. The system consists of several modules; a database that contains secrets, configuration, passwords and audit events, a service to establish, monitor and record privileged sessions, a user directory to maintain local users and groups and a job engine to execute scripts and tasks.

Privileged Account Management

A secure AES 256-bit encrypted database that contains records which can be stored, shared and used without disclosing the actual privileged account or its secrets (passwords, certificates or keys).

Privileged Session Management

The ability to establish a privileged session to an underlying system (Windows, Unix, Linux, Mac) through a standard web browser while providing the means to monitor, join, record or terminate this session.

Privileged Job Management

Schedule, automate or execute on demand jobs to privileged systems without embedding the secrets in scripts or sharing them with untrusted users.

Software Components

To accomplish the requirements above, XTAM needs to install, configure and run the following software and services. These components are deployed during the installation process (single server deployment) or they can be distributed to multiple servers (farm deployment) to scale performance. Single server deployments can be scaled to farm deployments when additional resources become needed.

Architectural Diagram

XTAM sits within the firewall in its own SSL secured network. Client computers make requests, establish sessions and run jobs from inside or outside the firewall to computers also located inside or outside the

firewall using only their native web browser of choice. The Database of Secrets secures all records using an AES 256-bit encrypted protocol and only delivers these secrets to authorized remote requests.




Figure 1: Xton Access Manager Architectural Diagram



Services

Depending on your installation, the following services may be deployed to Automatically startup on your computer.

Service	Function
PamDirectory	Provides the directory service to manage local users and groups in XTAM.
PamManagement	Provides the service to manage the XTAM system.
PamSession	Provides the service to establish, maintain, control and record privileged sessions via a user's web browser.

Table 1: XTAM Services

Active Directory or LDAP Integration

Integration with Active Directory or LDAP provides the ability to add Active Directory Users or Groups to XTAM to manage or use the system. XTAM will use this Active Directory integration to

- Authenticate user logins
- Read Active Directory group membership
- Reset Active Directory passwords

Planning your Installation and Deployment

The key to a successful deployment is proper planning. Before you begin the installation process, please understand the following.

- The full scope of your user base. How many individual users will be working with XTAM and of those how many will be accessing the system at the same time. This will help in planning the amount of resources and servers that are required to run the system efficiently.
- Setup a test environment. This could be a basic single server VM or a dedicated workstation, but ensure XTAM is configured and running in your test environment before deploying to production. This can also act as a test bed for future software releases.
- Decide if you want to integrate with Active Directory or LDAP for users, groups and authentication or to maintain a local directory for users and groups.
- If you want to use a SSL certificate to ensure a secure connection between the client computers and XTAM, then it is highly recommended to obtain and deploy the certificate prior to installation.

Installing Xton Access Manager

This section will work through the process of installing Xton Access Manager to a Windows computer.

System Requirements

The following are minimum requirements to use XTAM for Single Server and medium use Production farms. Please contact us to discuss architecture and system recommendations for large scale farm deployments.

	Single Server, Test or Quick Trial	Medium Use Production Farm
Windows O/S	Windows Server 2008 R2+ / Windows 7+	Windows Server 2008 R2+
Other O/S	Red Hat, Ubuntu, Debian, CentOS	Red Hat, Ubuntu, Debian, CentOS
Database	Included *	MS SQL, MySQL, Oracle, PostgreSQL
Servers	1	5 (1 database, 2 job engines with session manager role, 1 user directory, 1 load balancer)
Memory	2GB+	4GB+
Disk Space	10GB+	10GB+

Table 2: System Requirements

*For Single Server, Test or Quick Trial deployments the recommendation is to use the included, internal database however you can use any of the other supported databases that are available to you.

Software Requirements

- Web Browsers (*latest version is recommended if not specified*)
 - Internet Explorer 10+, Windows Edge, Google Chrome, Mozilla Firefox or Apple Safari

External Database

The default installation includes an internal database that can be deployed. If you would prefer to use an existing database in your environment, the following are supported. Please be prepared to supply a valid connection string to your database as well as an appropriate user and password to successfully establish this connection. *Please contact your Database Administrator if you need assistance.*

- Apache Derby version 10.12.1.1+
- Microsoft SQL version 2008+
- MySQL Community or Enterprise Edition version 5.7+
- Oracle version 11.2+
- PostgreSQL version 9.5+

Installation

The following section will describe each option that is available in the installation wizard. To begin, run the setup file from your computer and follow through the wizard. Depending on the options selected, the following configuration parameters may be available.



Figure 2: Setup Welcome Page

License Agreement

Read and accept the license agreement by clicking the **I Agree** button to proceed. The license agreement must be accepted to install the software.




Figure 3: Read and Accept the License Agreement

Components

Choose from the available list of components to install on this computer. If you are looking to deploy a quick test environment, the recommendation is to leave the default options and simply click **Next** to continue. If you would like to customize the installation, then please review the following sections to understand the purpose of each component. When you are finishing customizing your component selection, click **Next** to continue.

Please note that while you can choose to not install some components on this system, they may still be required for proper software operations. For example, you may wish to install the Session Manager service on another system for performance optimization. In this situation, you would choose to not deploy this service on your primary host and then after this initial installation is complete, you would then run this same installer on your other host and only choose the Session Manager option. Later on in the configuration of the software, you will have the ability to define which workstation is running each service.




Figure 4: Choose Components

Internal Database

This option will define which database to use. When enabled (checked) the installation will deploy, configure and use its internal database. If disabled (unchecked), you will be prompted to supply an existing database in your environment to use (connection string, user and password). Please review the requirements section for more information about [External Database](#) support.

For single server or test environments, the recommendation is to enable (check) this option to use the included database.

Directory Service

This option will define which user store to use. When enabled (checked) the installation will include a local user store that can be used to create users and groups and a database to secure the master password. When disabled (unchecked) the installation will not deploy this component to the computer; however, this is a required component so it must be deployed to only one other computer and configured post installation in XTAM.



To install this component on another host, simply run the installer on that system and enable (check) this option.

The recommendation is to include this option during installation.

Application GUI

This option will define the deployment of the XTAM interface (GUI). When enabled (checked) the installation will include the manager interface (GUI) to this host computer. When disabled (unchecked) the installation will not deploy the GUI requirements to this host computer.

To install this component on another host, simply run the installer on that system and enable (check) this option.

The recommendation is to include this option during installation.

Job Engine

The Job Engine is required to execute background operations like discovery queries and password resets. This option defines the deployment of a worker role to this host computer. When enabled (checked) a Job Engine role will be deployed. When disabled (unchecked) a Job Engine role will not be deployed to this computer.

To install this component on another host, simply run the installer on that system and enable (check) this option.

Please note that at least one job engine should be present in the farm to execute password reset, remove script execution or discovery queries.

The recommendation is to include this option during installation.

Session Manager

The Session Manager component is required to establish, control and record privileged sessions. This option defines the deployment of a session manager service to this host computer. When enabled (checked) a session manager service will be deployed, configured and run from this host. When disabled (unchecked) a session manager service will not be deployed.

To install this component on another host, simply run the installer on that system and enable (check) this option. Review the following section if you intend to install Session Manager on a remote computer(s): [Remote Session Manager Configuration](#)

Please note that if a session manager service is not defined during installation, you will need to add one during system configuration before sessions can be established.

The recommendation is to include this option during installation.



Federated Sign-In

This option defines the deployment of a federated sign-in component that can be used to establish user authentication. When enabled (checked) you will need to supply your federated sign-in server connection parameters. When disabled (unchecked) a SSO server will not be configured and the default login authentication will be used.

To install this component on another host, simply run the installer on that system and enable (check) this option.

This is an advanced option and should only be included if necessary. For single server or test environments, the recommendation is to not include this option.

Load Balancer

The option defines the configuration of load balancing within IIS on this computer. When enabled (checked) load balancing will be configured in IIS. When disabled (unchecked), load balancing will not be configured.

To install this component on another host, simply run the installer on that system and enable (check) this option.

This is an advanced option and should only be included if necessary. For single server or test environments, the recommendation is to not include this option.

Installation Location

Enter or select the location where the XTAM software will be downloaded and installed. Click **Next** to continue.





Figure 5: Choose Installation Location

System Administrator

Enter the required parameters to create your default System Administrator login to XTAM. The account specified here may be used as the first System Administrator, so be sure to choose a memorable login (default login is “xtamadmin”) with a strong password (maximum of 30 characters). Both the user login and password will be displayed later when they can be saved to a file for safe keeping. Click **Next** to continue.



Xton Access Manager Setup

System Administrator
Please define the account which will become a system administrator in the software.

Admin User Login: xtamadmin

Admin First Name: Service

Admin Last Name: Administrator

Password: [Masked]

Repeat Password: [Masked]


Copyright (c) 2017 Xton Technologies, LLC

< Back Next > Cancel

Figure 6: Create XTAM System Admin Account

SSO Connect

To define a managed path to be used with federated sign in, enable (check) the **Enable SSO** box and then enter that valid path in the **Managed Path** field. If XTAM is to be used with an SSL certificate, then this option should be enabled and the managed path needs to be defined with a secure path (for example, <https://host.example.com>). Click **Next** to continue.



The screenshot shows a Windows-style window titled "Xton Access Manager Setup". The window has a title bar with standard minimize, maximize, and close buttons. The main content area is titled "Federated Connection" and includes the instruction "Define your Federated Server Connection." Below this, there is a checkbox labeled "Enable SSO" which is checked. To the right of the checkbox is a text input field labeled "Managed Path". Below the input field, there is a note: "Please enter the managed path to your web application that is used for federation (for example, https://host.example.com)". At the bottom of the window, there is a copyright notice: "Copyright (c) 2017 Xton Technologies, LLC". Below the copyright notice are three buttons: "< Back", "Next >" (which is highlighted with a blue border), and "Cancel".

Figure 7: Enable and Define Federated Connection (optional)

Load Balancer

If you chose to include the Load Balancer module on this computer, then you will need to provide the IIS Host now. Enter the name in the provided field and click **Next** to continue.




Figure 8: Configure your IIS Load Balancer

External Database

If the Database option was left disabled (unchecked) earlier, then you will now need to define your connection to your external database. Select your **Database** type and then enter the required parameters to establish a successful connection. If further assistance is required, please contact your database administrator. Click **Next** to continue.

Example strings are listed below.

- Apache Derby
 - Example connection string: db-host or db-host:port
- Microsoft SQL Server
 - Example connection string: db-host or db-host:port
- MySQL
 - Example connection string: db-host or db-host:port
- Oracle
 - Example service: //db-host/db-service
 - Example instance: //db-host:port:SID
- PostgreSQL
 - Example connection string: db-host or db-host:port




Figure 9: Connect to an External Database (optional)

Active Directory Integration

Optionally, you may choose to integrate XTAM with your existing Active Directory or LDAP server. Enter your **LDAP Server** FQDN, your Active Directory or LDAP **User** ([user@domain.com](#) or domain\user), its **Password** and then click **Connect**. If the connection is successful, this user may become a System Administrator in XTAM and you may continue. If you cannot or do not want to integrate with Active Directory or LDAP, you may leave these parameters empty. Click **Next** to continue.




Figure 10: Active Directory or LDAP Server Integration

Summary

The summary screen will display all the services, accounts and password that were created during installation. It is **extremely** important that all this information be saved to a file and kept in a safe location. The Master Password displayed will be required in a “break glass” or database transfer scenario and no one will be able to identify nor update this password if it is ever lost.




Figure 11: Summary Screen with Passwords (save this information to a file for safe keeping)

If you do not see these passwords or receive any errors in this Summary screen the installation was not successful. Complete the installation and then uninstall to try again. Do not initialize Xton Access Manager without a successful deployment and a safe and secure copy of the logins and passwords shown in the example Summary screen.

The Next button will be disabled until all the services have been started and are available on this computer. This process may take a few minutes to complete. When the services are ready, check the box to confirm that your passwords have been saved to a file in a safe location and then the Next button will become available. Click **Next** to continue.




Figure 12: Summary Screen with Confirmation

NOTE: It is extremely important that all the passwords displayed in this section are saved to a file and this file is stored in a safe location. These passwords cannot be retrieved by Xton Technologies or anyone else once the installation is complete.

Completing the Installation

On the final page, confirmation that the installation has been completed will appear. Enable (check) the box to launch the sign-in page or disable (uncheck) the option to not open the page. Click **Finish** to close the installation wizard. The software is now installed.

The default location for XTAM is <http://localhost:8080/xtam>




Figure 13: Installation Complete

Logging into Xton Access Manager

Open your web browser and navigate to the login screen of XTAM or double click the shortcut on your desktop. At the login prompt, you can sign in with one of the following system administrator logins:

- The [System Administrator](#) account that was created during the installation process.
- The [Active Directory or LDAP account](#) that was (optionally) used to establish integration during the installation process.

Enter the System Admin user and password and click the Login button. Upon successful login, you will be directed to the initialization page of XTAM. The account used as the first login will become a System Administrator.

Initialize

The first login (and only the first) after a new installation will require a system initialization. When logged in for the first time, click the Initialize button to begin this process. During this time, the system

will create all its needed configuration in the database and services. Depending on the complexity of your configuration, this process may take anywhere from a few seconds to 1-2 minutes to finish.

This is the application initialization page

Clicking the button below will initialize the application database with the initial data. Currently logged in user Service Administrator will become the application administrator.




Figure 14: XTAM “first-time” Initialization

When the initialization is complete, the system will redirect you to the landing page. You should see a few menu headings on the left side including Records, Administration and Management indicating that the process is complete.





Figure 15: Initialization Complete

License Registration

If you have a license key, then you should activate it now. Navigate to Administration > Settings > Registration. On the registration screen, copy and paste your key into the “Activation Code” field and then click **Automatic Registration**. When the license is retrieved successfully (status should display

“License is Valid”), click the **Save License** button to finalize. The software is now activated and ready for use.



The screenshot shows a web interface for license activation. At the top right, there are three buttons: "Save License", "Automatic Registration", and "Manual Registration". Below these, the "Status" field displays "License is Valid". The "Activation code" field shows "c81" followed by a redacted area. The "License" field contains a text area with the following content: "-----LICENSE BEGIN-----", "Activation:c81", "Product:PAM", "HUB:XtonTech", and "Client:ck" followed by a redacted area.

Figure 16: License Activation

Manual Registration

If the computer is not connected to the internet or cannot establish a connection to the license server for registration, then the following procedure will register the software manually.

1. Click the Manual Registration button. A new browser window will appear.
2. Copy or transfer this URL to a computer with an internet connection and load the page.
3. Select the copy the license information between and including the LICENSE BEGIN header and LICENSE END footer.
4. Save this information to a file or paste it directly into the “License” field in XTAM.
5. Click the Save License button.
6. The license status will read “License is Valid” and the software is now registered.

Uninstalling Xton Access Manager

You can uninstall XTAM by simply running the uninstall executable located in its installation directory.

Uninstaller

First, logout and close any open Sessions in XTAM as well as any open sessions in your Web Browser. Double click the uninstall executable and follow the wizard. When the wizard completes, the software and its services will be removed from your computer.

If you deployed additional services to other servers, then you will need to run the uninstall executable on each of these computers to remove the components.

Database Cleanup

If you have configured XTAM with the use of an external database, then you will need to manually remove these database objects. Please contact your database administrator for assistance.

Appendix

Remote Session Manager Configuration

When installing the Session Manager component on a remote Windows computer(s), then the following steps should be taken.

1. Ensure that XTAM is Installed and configured on your master computer.
2. Run the setup file on the remote computer where Session Manager is to be deployed.
3. On the Welcome screen, click **Next** to begin the installation on this computer.
4. Read and accept the License Agreement by clicking the **I Agree** button to continue.
5. Uncheck all Component options except Session Manager. Click **Next** to continue.




Figure 17: Select the Session Manager Component

6. Choose your installation location and click **Next** to continue.
7. When prompted, locate and select the certificate bundle that was deployed to your master computer where XTAM was installed earlier. Click **Next** to continue.




Figure 18: Locate and Select certbundle.zip

- a. The certificate bundle is in the root XTAM installation directory on your master computer. The default file location is C:\xtam\certbundle.zip
- b. You may select the zip file from this default location (if possible), copy it to a shared network location or simply copy the zip file to this remote computer and select it locally.

NOTE: This step is optional, so if you wish to not supply the certificate you may simply click Next to continue. By skipping this option, you are acknowledging that the communication between XTAM on the master computer and this remote Session Manager computer will not be secured. Because of this, it is recommended that you supply the certificate when prompted and do not skip this step.

8. The Session Manager service will now startup on this computer. Click **Next** to continue.
9. Click **Finish** to complete the installation.